


Data Create	2015/08/19	Release Note	<input type="checkbox"/> Internal <input checked="" type="checkbox"/> External
Category	FAQ	Product Group	IAG
Function	File Server	Related OS	CE
Related Product	UNO-1110		

[Abstract]

How to Use File Server on UNO-1110(CE6.0).

[Solution]

1. After go into UNO-1110's Remote Management Tool, click "Add/Del Network Adapter". Select the IP that UNO-1110 is using. Then, click "Submit Query".



2. Click "Add/Del Users" to create or delete user.

Windows CE Remote Management Tool

Home

► Device Management

► Security

Add/Del Users

Add/Del Share

► Printer

Use this page to Add/Delete users.

Add/Modify User

User	<input type="text" value="cat"/>
Password	<input type="password" value="..."/>
Password Verify	<input type="password"/>
<input type="button" value="Add New"/>	

Delete Users

ADMIN	<input type="button" value="Delete"/>
dog	<input type="button" value="Delete"/>
cat	<input type="button" value="Delete"/>

3. Click "Add/Del Share" to assign specific file to specific user.

Type-in file name and click "Add". For example, I type-in "Example" and "Test" after \Windows and \HardDisk.

Windows CE Remote Management Tool

Home

► Device Management

► Security

Add/Del Users

Add/Del Share


► Printer

Use this page to add and remove shares

Available Shares

\Windows	Example	<input type="button" value="Remove"/>	<input type="button" value="Permissions"/>
\Temp	<input type="text"/>	<input type="button" value="Add"/>	
\Program Files	<input type="text"/>	<input type="button" value="Add"/>	
\My Documents	<input type="text"/>	<input type="button" value="Add"/>	
\Application Data	<input type="text"/>	<input type="button" value="Add"/>	
\Recycled	<input type="text"/>	<input type="button" value="Add"/>	
\HardDisk	Test	<input type="button" value="Remove"/>	<input type="button" value="Permissions"/>
\Network	<input type="text"/>	<input type="button" value="Add"/>	

- Click "Permissions". Then, Select "Allow" or "Deny" to different Users. Finally, click "Update" and "Done" so the change can be saved.



- Open a file manager on your Developing Computer and type-in IP address "\\Target IP Address". After log-in, you will have access right to these files.

