

Advantech AE Technical Share Document


Date	2020 / 09 / 28	Release Note	☐ Internal ■ External
Category	■ FAQ □ SOP	Related OS	Windows 7/8/10
Abstract	What is the difference between PenMount's Mouse Device and Digitizer		
	Device?		
Keyword	PenMount, touch, touch screen, Mouse Device, Digitizer Device		
Related Product	All panels with PenMount controller installed		

Brief Solution:

The PenMount device driver supports two types of device type configurations: mouse and digitizer. The mouse device type is compatible to all Windows operating systems while the digitizer device only works on systems that support Tablet PC Input.

Starting from PenMount Universal Driver V2.4, the setup program will allow users to choose to install the device as a "Mouse Device" or "Digitizer Device" on systems that support Digitizers. A message box will pop up as following:

Please select "YES" for installing PenMount as mouse device; select "NO" for digitizer device.





In general, installing the PenMount controller as a mouse device is recommended. If you wish to use the Tablet PC Input features in Windows 7 / 8 / 10, you may need to choose to install the PenMount device as a digitizer.


Device Type	Mouse Device	Digitizer Device	
Supported Operating	Windows	Windows XPT/	
System	2000/XP/Vista/7/8/10	Vista/7/8/10	
PenMount Control Panel	Launch in PenMount	Launch with desktop icon	
	Monitor Menu		
Calibration	Supported PenMount 4/9/16/25 calibration		
Multiple Monitor	Supported	Supported	
	(Use PenMount monitor	(Configured in Tablet PC	
	mapping)	Settings)	
Flicks (Windows 7)	Not supported	Supported	
Right Button	Supported	Supported	
	(Use PenMount Press and	(Use system Press and	
	Hold / Right Click utility)	Hold gesture)	
Edge Compensation	Supported		
Touch Beep Sound	Supported		
Operating Modes	Supported	Not Supported	

Operation Mode	Description
Pen Input Emulation	Select this mode and mouse will emulate Windows Vista pen input device operation, by which no mouse event will be sent until the touch is dragged out of range or released from the screen.
Mouse Emulation	Select this mode and mouse functions as normal and allows dragging of icons.
Click on Touch	Select this mode and mouse only provides a click function, and dragging is disabled.
Click on Release	Select this mode and mouse only provides a click function when the touch is released.




There are several differences between the mouse version and the digitizer version of the PenMount Control Panel.

For digitizer devices, please check the "Tablet PC Settings" in the system Control Panel for mapping monitors.



Take the PenMount 6000 for example, the device configuration window will appear after clicking on the "PenMount 6000 USB" or "PenMount 6000 RS232" icon in the PenMount Control Panel.





Supported operating system

The PenMount Windows Universal Driver supports the following Windows operating systems. The PenMount device driver can be installed as a digitizer on systems that provides Tablet PC support.

	Operating System	Tablet PC Support	Multi-Touch Support
Windows Desktop	Windows 2000		
	Windows XP		
	Windows XP Tablet PC Edition 2005	Yes	
	Windows Vista	Yes	
	Windows 7	Yes	Yes
	Windows 8 / 8.1	Yes ₁	Yes
	Windows 10	Yes	Yes
Windows Server	Windows Server 2003 / 2003 R2		
	Windows Server 2008 / 2008 R2	Yes ₂	
	Windows Server 2012 / 2012 R2	Yes	Yes
	Windows Server 2016	Yes	Yes
Windows Embedded	Windows XP Embedded		
	Windows Embedded Standard / POSReady 2009		
	Windows Embedded Standard / POSReady 7	Yes ₃	Yes ₄
	Windows 8 / 8.1 Embedded Standard / Industry	Yes	Yes
	Windows 10 IoT Enterprise	Yes	Yes

¹ For Windows 8 / 8.1 with OEM Licenses, need to update KB3095649 for multi-touch support.

- 3 Only WES7P SKU provides Tablet PC support.
- 4 Only WES7P SKU provides Tablet PC support.

² Must manually install tablet pc service from control panel.